



Stock Import on cloud - sFTP

What is needed to access cloud through sFTP :

- To share sFTP with anyone (or any system) there is a need of having an account in <https://accounts.magento.cloud/>
 1. first go to: <https://account.magento.com/customer/account/create/> and create account;
 2. after creating an account go to <https://account.magento.com/cloud/customer/login/> and log in using Magento Account credentials;
 - a. this will create the same account in cloud infrastructure;
- That account **must have ssh key connected in its account configuration**;



- Add SSH Key



- to generate ssh key use methods described in this article: <https://confluence.atlassian.com/bitbucketserver/creating-ssh-keys-776639788.html>
- After that account can be added to the project;
 - to add this account to a project we must know e-mail that was provided during account creation;
- Every new env. has this turned on - and can be accessed after obtaining all access rights;
 - An account with SSH key will always be added to all existing environments - there will be no need to create new accounts for different envs.

For Dev env.:

- username: **ynti7vfvb5g-dev-upgrade-3sukxri--yale**
- host: **ssh.eu-3.magento.cloud**
- port: **22**
- password: none
- **+ SSH key - choose ssh key authentication;**

Stock file location:

- uk: /app/var/import/stock.csv
- fr: /app/var/import/stockfr.csv
- pt: /app/var/import/stockpt.csv
- ib: /app/var/import/stockib.csv
- it: /app/var/import/stockit.csv
- nl: /app/var/import/stocknl.csv
- de: /app/var/import/stockde.csv
- za: /app/var/import/stockza.csv

For Integration env. (legacy UAT):

- username: **ynti7vfvb5g-integration-5ojmyuq--yale**
- host: **ssh.eu-3.magento.cloud**
- port: **22**
- password: none
- **+ SSH key - choose ssh key authentication;**

Stock file location:

- uk: /app/var/import/stock.csv
- fr: /app/var/import/stockfr.csv
- pt: /app/var/import/stockpt.csv
- ib: /app/var/import/stockib.csv
- it: /app/var/import/stockit.csv
- nl: /app/var/import/stocknl.csv
- de: /app/var/import/stockde.csv
- za: /app/var/import/stockza.csv

For Staging env.:

- username: 1.ent-ynti7vfvb5g-staging-5em2ouy
- host: **ssh.eu-3.magento.cloud**
- port: **22**
- password: none
- **+ SSH key - choose ssh key authentication;**

Stock file location:

- uk: /app/ynti7vfvb5g_stg/var/import/stock.csv
- fr: /app/ynti7vfvb5g_stg/var/import/stockfr.csv
- pt: /app/ynti7vfvb5g_stg/var/import/stockpt.csv
- ib: /app/ynti7vfvb5g_stg/var/import/stockib.csv
- it: /app/ynti7vfvb5g_stg/var/import/stockit.csv
- nl: /app/ynti7vfvb5g_stg/var/import/stocknl.csv
- de: /app/ynti7vfvb5g_stg/var/import/stockde.csv
- za: /app/ynti7vfvb5g_stg/var/import/stockza.csv

For Production env.:

- username: 1.ent-ynti7vfvb5g-production-vohbr3y
- host: **ssh.eu-3.magento.cloud**
- port: **22**
- password: none
- **+ SSH key - choose ssh key authentication;**

Stock file location:

- uk: /app/ynti7vfvb5g/var/import/stock.csv
- fr: /app/ynti7vfvb5g/var/import/stockfr.csv
- pt: /app/ynti7vfvb5g/var/import/stockpt.csv
- ib: /app/ynti7vfvb5g/var/import/stockib.csv
- it: /app/ynti7vfvb5g/var/import/stockit.csv
- nl: /app/ynti7vfvb5g/var/import/stocknl.csv
- de: /app/ynti7vfvb5g/var/import/stockde.csv
- za: /app/ynti7vfvb5g/var/import/stockza.csv